Intersil PMBus Interface Installation Directions (Windows 7 x86 and x64):

- 1) Before proceeding, locate the "PMBus Interface Install Guide Win7 x86 and x64" on Intersil's website: intersil.com/powernavigator.
- 2) Plug the USB Dongle into the computer. You should see the green led on the dongle light up.
- 3) You may see a popup from the system tray that looks like this:



Ignore this error, we will resolve it by manually installing the device driver.

4) Go to the Start Menu, click on Control Panel



5) In Control Panel, click on "View devices and printers"



6) Scroll down the list of devices to find the Intersil Zilker Labs PMBus Interface. Double click on its icon.



7) In the Device information menu, click Properties:

Zilker Labs PMBus Interface Properties	×	
General Hardware		
Zilker Labs PMBus Interface		
Device Functions:		
Name	Туре	
Ma Zilker Labs PMBus Interface	Other devices	
Device Function Summary		
Manufacturer: Unknown		
Location: Port_#0001.Hub_#0001		
Device status: The drivers for this device	are not installed. (Code 28)	
	Properties	
ОК	Cancel Apply	

8) In the Properties menu, you may need to click the "Change Settings" menu. Click this.

Zilker Labs	PMBus Interface	Properties	×
General	Driver Details		
	Zilker Labs PMBu	s Interface	
	Device type:	Other devices	
	Manufacturer:	Unknown	
	Location:	Port_#0001.Hub_#0001	
The of th	e is no driver selecte ent.	e are not installed. (Code 28) ed for the device information set or evice, click Update Driver.	*
		Update Driver	*
	Change settings		
		ОК Са	ncel

9) You should now see the "Update Driver..." button available. Click it.

lker Lab	s PMBus Interface	Properties	23
General	Driver Details		
2	Zilker Labs PMB	us Interface	
	Device type:	Other devices	
	Manufacturer:	Unknown	
	Location:	Port_#0001.Hub_#0001	
The elen	re is no driver select nent.	ce are not installed. (Code 28) ted for the device information set or device, click Update Driver.	*
		Update Dri	ver
		ОК	Cancel

10) You will see two options for driver installation. Select "Browse my computer for driver software"



11) Browse to the ZL_USB_Drivers directory, and click Next to install the drivers.



12) You will see a security warning about the driver installation. This is because we use a renamed version of a WHQL-certified driver. Click "Install this driver software anyway" to continue.



13) Installation should now be complete. You may now connect the usb dongle to your Intersil Zilker Labs devices and run

