

[Upgrade to revision]

R20TS0417EJ0100

Rev.1.00

CS+ Device Information for RX Family V3.01.01

Apr. 16, 2019

Outline

We have updated the CS+ device information for RX family from V3.00.00 to V3.01.01.

1. Products and Versions to Be Updated

- CS+ Device Information for RX and V1.04.00 or later
- CubeSuite+ Device Information for RX (CubeSuite+ DevInfo_RX) V1.03.00 or earlier

To check the version of "CS+ Device Information for RX" or "CubeSuite+ DevInfo_RX", follow the steps under "Components" at the URL below.

<https://www.renesas.com/cs+ ver>

2. Description of the Update

The main feature of the update is described in the following section. For details, refer to the following URL:

(The information will be available on April 22.)

https://www.renesas.com/cs+/eng/CSPlus_DevInfo_RX.html

2.1 Addition of Supported Devices

Supported devices for the following group has been added.

-RX family RX66T group

R5F566TFAxFP, R5F566TFBxFP, R5F566TFCxFB, R5F566TFCxFP,
R5F566TFExFP, R5F566TFFxFP, R5F566TFGxFB, R5F566TFGxFP,
R5F566TKAxFP, R5F566TKBxFP, R5F566TKCxFB, R5F566TKCxFP,
R5F566TKExFP, R5F566TKFxFP, R5F566TKGxFB, R5F566TKGxFP

3. Updating Your Product

Online updating is available free of charge. Update method varies depending on the version of your CS+.

Note: A license for C/C++ Compiler Package for RX Family V2 (CC-RX) cannot remove the restrictions on the evaluation edition of C/C++ Compiler Package for RX Family V3 (CC-RX). If you wish to lift the restrictions on C/C++ Compiler Package for RX Family V3 (CC-RX), you need to purchase the commercial edition of C/C++ Compiler Package for RX Family V3 (CC-RX).

3.1 For CS+ V3.00.00 or Later

To update your program, use either of the following methods:

- (1) On the Start menu, select Programs → Renesas Electronics CS+ to start the Update Manager.

(This service will be available on April 22.)

Note: If your CS+ has been launched with rapid startup enabled, exit the CS+ once, and then run the Update Manager.

If the CS+ is resident in the notification area of Windows (system tray) due to rapid startup, an error occurs and produces the following message:

M0120001

"CubeSuiteW+.exe"

Installation is suspended because "CubeSuiteW+.exe" is running.

It will be resumed next time you start the tool.

- (2) Download and install the desired software tools from the following URL:

(The program will be available on April 22.)

https://www.renesas.com/cs+_download

3.2 For CubeSuite+ V2.00.00 to 2.02.00

Update your program in the same way as described in section 3.1 above.

3.3 For CubeSuite+ V1.03.00 or Earlier

Download and install the evaluation edition of CS+ CC-RX V8.01.00 from the following URL. Then, update your program in the same way as described in section 3.1 above.

(The program will be available on April 22.)

https://www.renesas.com/cs+_download

Revision History

Rev.	Date	Description	
		Page	Summary
1.00	Apr.16.19	-	First edition issued

Renesas Electronics has used reasonable care in preparing the information included in this document, but Renesas Electronics does not warrant that such information is error free. Renesas Electronics assumes no liability whatsoever for any damages incurred by you resulting from errors in or omissions from the information included herein.

The past news contents have been based on information at the time of publication. Now changed or invalid information may be included.

URLs in Tool News also may be subject to change or become invalid without prior notice.

Corporate Headquarters

TOYOSU FORESIA, 3-2-24 Toyosu, Koto-ku, Tokyo 135-0061 Japan

www.renesas.com

Contact information

For further information on a product, technology, the most up-to-date version of a document, or your nearest sales office, please visit:

www.renesas.com/contact/

Trademarks

Renesas and the Renesas logo are trademarks of Renesas Electronics Corporation. All trademarks and registered trademarks are the property of their respective owners.